

ContactLab DataExchange Configuration Guide

Version <201705.1>

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Revision History

Date (yyyy-mm-dd)	Version	Description	Author/s
2009-10-20	200910.1 to 201101.1	Older revisions	Misc
2011-01-31	201101.2	Typos removed	Davide Migliavacca
2011-07-13	201107.1	(Not published) Exporter: medium field added	Daniele Zuccalà
2012-01-16	201201.1	New DataExporter events added, DataCollector module added, DataImporter limitations added, several minor changes	Matteo Bordoni
2012-03-15	201202.1	Subdetails for "optout" event updated, "title" field added to DataExporter delivery dataset	Matteo Bordoni
2013-01-28	201203.1	Poller option, WURFL device detection data available in Exporter	Davide Migliavacca
2013-09-11	201309.1	Support for Robinson Lists in DataExporter, chapter 7 updated	Giorgio Cantoni
2014-01-27	201401.1	Exporter enhancements	Davide Migliavacca
2016-01-25	201601.1	Non-email message exports, Axway CFT	Davide Migliavacca
2017-01-30	201701.1	DataExporter enhancements	Davide Migliavacca
2017-05-03	201705.1	JDBC connectors de-supported	Davide Migliavacca

Table of contents

1. Introduction	4
2. The DataUpdater module	5
2.1 Supported file formats and datasource structure	5
2.2 Location of the datasource	7
2.3 Operation modes	8
2.4 Additional tools and configuration options	9
2.5 Execution and reporting options	10
3. The DataDem module	11
3.1 Supported file formats and datasource structure	11
3.2 Location of the datasource	13
3.3 Operation modes	13
3.4 Execution and reporting options	15
4. The DataImporter module	16
4.1 Supported file formats and datasource structure	16
4.2 Location of the datasource	17
4.3 Operation modes	18
4.4 Limitations	18
4.5 Additional tools and configuration options	18

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

4.6	Execution and reporting options	19
5.	The DataCollector module	20
5.1	Supported file formats and datasource structure	20
5.2	Access and location of the datasource	20
5.3	Additional tools and configuration options	21
5.4	Execution and reporting options	21
	The DataExporter module	22
5.5	Supported file formats	22
5.6	Location of the destination	23
5.7	Operations mode and available information	23
5.8	XML file format specifications	31
5.9	Execution and reporting options	33
5.10	Data subject to variation over time	33
6.	The DataDisplacer module	34
6.1	Supported file formats and destination structure	34
6.2	Location of the destination	35
6.3	Operation modes	36
6.4	Additional tools and configuration options	36
6.5	Execution and reporting options	36
7.	Managing DataExchange modules in ContactLab UI	37
8.	Standard ETL function library	40
8.1	Basic::stringDateFormat	40
8.2	Basic::getDomainFromEmailAddress	40
8.3	Basic::getIntFromBoolean	40
8.4	Basic::trimChars	40
8.5	Basic::force	40
8.6	Basic::integerToBinaryString	40
8.7	Basic::semicolonSeparated2bitmask	40
8.8	FieldValueMaintainer::dontChangeIFFieldValueIS	40
8.9	FieldValueMaintainer:genericTranscode	40
8.10	LookupTable::checkField	40
8.11	Zone:: <i>miscellanea</i>	41
9.	DataExchange Post-Actions	41
9.1	Chained DataExchange Modules	41
9.2	Start a Delivery after a DataExchange Operation	41
9.3	DB Fitness	41
9.4	Duplicate Remover	41
10.	Diagnostics messages	42
11.	Frequently Asked Questions & Answers	45
12.	Contacts	47

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

ContactLab DataExchange Configuration Guide

1. Introduction

The setup of a messaging *campaign* in ContactLab involves as a prerequisite the setup of a database containing at least all *recipients* of the campaign. This database has to be setup inside the ContactLab platform.

ContactLab's platform supports a number of alternatives for this task, trying to accommodate the requirements of customers by allowing the configuration of completely automated and safe ways of transferring a large number of recipients and related data as a viable alternative to simple upload operations via the web UI.

Using the platform's application modules, it is possible to automatically load or update databases in preparation for future campaign deliveries, and also automatically download standard or customized reporting datasets for customers' consumption.

DataExchange is a name for a number of application modules dealing with automated data transfer to and from ContactLab, possibly transforming data while it is being transferred, and the automatic setup of filters to be used in campaign definitions. All of this, without the need of accessing or operating on the web UI.

Data transfer can be bi-directional and utilize different protocols and methodologies according to each customer's unique needs and skills available in-house. Recipient databases or reporting datasets are among the types of data available through DataExchange configurations.

Four different DataExchange components (modules) are available to be used according to specific situations:

- **DataUpdater** : it allows to perform managed incremental updates to a specific recipient (user) database in ContactLab, with data coming from an external source.
- **DataDem** : it allows the creation of customized delivery filters in ContactLab.
- **DataImporter** : it allows to load a specific recipient (user) database in ContactLab from an external source.
- **DataCollector** : it allows to merge data from multiple text files and trigger the execution of a DataExchange module
- **DataExporter** : it allows to export data about campaigns summary or analytical data from ContactLab to a remote system, either as a CSV file, an XML file or directly posting data to a remote database.
- **DataDisplacer** : it allows to export data extracted from User Database hosted in ContactLab to a remote system, either as a CSV file or posting data to a remote database.


The abovementioned components do not only manage recipient data or events relating to deliveries (open, clicks etc.) – they can also deal with in-depth data such as ROI events, or any other event ContactLab can track, in order to let the customer easily setup *triggered* deliveries basing on specific conditions considering a multitude of unrelated facts coming from different systems.

The following chapters offer an in-depth review of the available DataExchange modules.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

2. The DataUpdater module

The DataUpdater module allows the maximum flexibility in updating user databases in ContactLab with data coming from external sources.



2.1 Supported file formats and datasource structure

The DataUpdater module needs a *datasource* providing data to be applied to the user database for any operation. The datasource can be generated in various formats, but there must exist a clear relationship among the datasource's structure and the user database's field definitions in ContactLab.

An additional and mandatory field must exist in the datasource and provide information on the *action* to be performed on a specific record (row) in the datasource itself. Not surprisingly, the expected name for this field is *action*, a text field assuming one of the following values: **I** (for **I**nsert), **U** (for **U**ppdate) and **D** (for **D**elete).

The following formats are supported:

- **CSV (comma separated value) file:** fields in the CSV file must correspond exactly both in ordering and datatypes to fields defined in the destination ContactLab user database. The field separator, string delimiter and line-ending character can be configured according to customer needs. An additional field (*action*) must always be present to tell the DataUpdater module what to do with the record (row) being examined.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Example (CSV file):

Let's suppose we have a user database in ContactLab (the *destination*) with the following structure and records:

"Subscribers to *gardening* newsletter"

ID	EMAIL	FIRSTNAME	LASTNAME	ADDRESS	PHONE	SEX
1	Jsmith@example.com	John	Smith	1, Rome St.	09941444	M
2	Rb@example.net	Robert	Bar	2, Bear Av.	10001433	M
3	Tinaf@example.org	Tina	Foo	3, Time Sq.	21199001	F

Please note: fictitious data

Let's further suppose data needs to be updated thusly: Rob Bar asked to be removed and will be deleted from the user database; Tina Foo changed its street address to "4, Past Sq."; and we have a new subscriber, Carly Fines. John Smith will remain as it is.

The following CSV-format datasource for DataUpdater will do the trick:

```
2;"Rb@example.net";"Robert";"Bar";"2, Bear Av.";10001433;"M";"D"\r\n
3;"Tinaf@example.org";"Tina";"Foo";"4, Past sq.";21199001;"F";"U"\r\n
4;"Carly.f@clab1.net";"Carly";"Fines";"10, Ten St.";67710221;"F";"I"\r\n
```

The final results in our user database:

"Subscribers to *gardening* newsletter"

ID	EMAIL	FIRSTNAME	LASTNAME	ADDRESS	PHONE	SEX
1	Jsmith@example.com	John	Smith	1, Rome St.	09941444	M
3	Rb@example.net	Robert	Bar	2, Bear Av.	10001433	M
4	carly.f@clab1.net	Carly	Fines	10, Ten St.	67710221	F

Please note: fictitious data

Although field separator, string delimiter and record separator are configurable, the name of the *action* field cannot be changed.

- **XML file:** a single "root" node (dataroot) must include child nodes (RECORD) for every record, and every record will contain tags with name corresponding the the user databases' field names. Values in these tags will be applied to records being imported by the DataUpdater module. Additionally, a mandatory *action* attribute must be specified for each RECORD node. For the XML format, it is possible to omit fields in an Update action block if their value must not necessarily be updated. The *master condition* field (read "2.3 Operation modes") must always be present. Fields can also be omitted in the D action.

Example (XML file):

This is the same example for the previous section (see above); we present the XML file needed to perform exactly the same set of operations. Please note the action attribute in the opening tag for the RECORD node. In this example, ID is the *master condition* (read "2.3 Operation modes"):

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

```
<?xml version="1.0" encoding="ISO-8859-1" ?>
  <dataroot>
    <RECORD ACTION="D">
      <ID>2</ID>
    </RECORD>
    <RECORD ACTION="U">
      <ID>3</ID>
      <EMAIL>Tinaf@example.org</EMAIL>
      <FIRSTNAME>Tina</FIRSTNAME>
      <LASTNAME>Foo</LASTNAME>
      <ADDRESS>4, Past Sq.</ADDRESS>
      <PHONE>21199001</PHONE>
      <SEX>F</SEX>
    </RECORD>
    <RECORD ACTION="I">
      <ID>4</ID>
      <EMAIL>carly.f@clabl.net</EMAIL>
      <FIRSTNAME>Carly</FIRSTNAME>
      <LASTNAME>Fines</LASTNAME>
      <ADDRESS>10, Ten St.</ADDRESS>
      <PHONE>67710221</PHONE>
      <SEX>F</SEX>
    </RECORD>
  </dataroot>
```

Example (remote table):

Once again, the "gardening" newsletter example is repeated. In order to reach the same result as previous example starting from the initial status of the subscriber user database, we'll need a properly built table in the customer database. This table has the same fields as our user database, plus the character string type "action" field assuming one of the predefined values (I, D or U):

Datasource table for 'gardening' database DataUpdater:

ID	EMAIL	FIRSTNAM E	LASTNAM E	ADDRESS	PHONE	SEX	ACTI ON
2	Rb@example.net	Robert	Bar	2, Bear Av.	10001433	M	D
3	Tinaf@example.org	Tina	Foo	4, Past Sq.	21199001	F	U
3	carly.f@clabl.net	Carly	Fines	10, Ten St.	67710221	F	I

Please note: fictitious data

Given this datasource, after the DataUpdater operation on the "gardening" user database, the result will be the same as for the first example (CSV, see above).

2.2 Location of the datasource

Once the datasource (file or remote database) is available, DataUpdater must be able to access it in order to perform its duty. The following approaches are available for this step:

- **Source file available via FTP/SFTP/FTPS:** Customer can provide ContactLab with access to a *secured and controlled* FTP or SFTP (the latter being strongly suggested) area provided specifically for this purpose. It is required specific credentials are used, dedicated to ContactLab.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

In case customer has difficulties providing an account with these characteristics, he/she can ask ContactLab to provide such an account on its own servers. ContactLab will provide credentials and instructions to connect to the customer-reserved area on its servers; customer will have to setup a process to upload the file(s) in this area.

- **Source file available via HTTP/HTTPS:** DataUpdater can also retrieve a named file from an http/https protected resource.
- **Source file available via Axway CFT.** Option available on request.

As an option, in addition to using an encrypted transport such as SFTP or HTTPS, it is also possible to use PGP/GPG public/private key pair encryption. Customer will have to provide its public key to ContactLab and ContactLab will provide its public key to customer.

As an option, files can be compressed using one of the industry standard ZIP, BZIP2 and GZIP compression formats. ContactLab will decompress them "on the fly" before processing their content.

As an option, compression and PGP/GPG encryption can be applied at the same time (in the specified order) on DataExchange files.

As an option, the module can be configured to *rename* the source file by automatically adding a timestamp with format YYYYMMDDHHmmss or *remove* it.

2.3 Operation modes

DataUpdater normally analyzes each and every record (row) in the datasource, matching the specified key (read further), and applies the *action* as specified in the properly named field in the source.

When updating (U) records being updated must already be present in the destination table. If they are not present, DataUpdater can either insert them as new or ignore them. These two different behaviours can be configured. With the auto-insert configuration, there is no need to use the 'I' operation, although using it might help troubleshooting as it clearly declares the intended operation and could help identify discrepancies between the master source and the user database in ContactLab.

Identifying records is an important part of the DataUpdater operations. It can be configured to use one or two fields as "keys"; we name this specification *Master Condition*.

Example (Master Condition):

Suppose we have the following user database as a destination. It is very similar to our "gardening" example, but we now have the ability to manage multiple newsletters using a *campaign_type* field. This means the same email might be present more than once in this table.

"Subscribers to all newsletters"

EMAIL	CAMPAIGN_TYPE	FIRSTNAME	LASTNAME	ADDRESS	PHONE	SEX
Jsmith@example.com	Gardening	John	Smith	1, Rome St.	09941444	M
Tinaf@example.org	Motors	Tina	Foo	3, Time Sq.	21199001	F
Jsmith@example.com	Motors	John	Smith	1, Rome St.	09941444	M

Please note: fictitious data

John Smith subscribed to both the Gardening and Motors-themed newsletters. At some point in time,

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

he updates his profile on the customers' website, updating his subscription data for Gardening (the site is organized by theme). Also, a new subscription arrives, and Tina Foo updates her street address.

The following datasource sample includes the changes we just described:

```
"jsmith@example.com";"Gardening";"John";"Smith";"2, New St.";09941444;"M";"U"\r\n
"tinaf@example.org";"Motors";"Tina";"Foo";"4, Past Sq.";21199001;"F";"U"\r\n
"carly.f@clab1.net";"Gardening";"Carly";"Fines";"10, Ten St.";67710221;"F";"I"\r\n
```

The *Master Condition* tells the DataUpdater module which key to use to identify records to be modified (updated). If the *Master Condition* in this example includes the EMAIL field only, *both* records for jsmith@example.com will be updated, producing the following result:

"Subscribers to all newsletters"

EMAIL	CAMPAIGN_TYPE	FIRSTNAME	LASTNAME	ADDRESS	PHONE	SEX
Jsmith@example.com	Gardening	John	Smith	1, Rome St.	09941444	M
Tinaf@example.org	Motors	Tina	Foo	3, Time Sq.	21199001	F
Carly.f@clab1.net	Gardening	Carly	Fines	10, Ten St.	67710221	F
Jsmith@example.com	Gardening	John	Smith	2, Rome St.	09941444	M

Please note: fictitious data

If, instead, the *Master Condition* includes the couple of fields [EMAIL, CAMPAIGN_TYPE], only one of two records for John Smith will be updated. The following will be the final result:

"Subscribers to all newsletters"

EMAIL	CAMPAIGN_TYPE	FIRSTNAME	LASTNAME	ADDRESS	PHONE	SEX
Jsmith@example.com	Gardening	John	Smith	1, Rome St.	09941444	M
Tinaf@example.org	Motors	Tina	Foo	3, Time Sq.	21199001	F
Carly.f@clab1.net	Gardening	Carly	Fines	10, Ten St.	67710221	F
Jsmith@example.com	Motors	John	Smith	1, Rome St.	09941444	M

Please notice the also the ADDRESS field for ['jsmith@example.com', Motors] remained '1, Rome St.' (instead of '2, Rome St.' since the update only identifies ['jsmith@example.com', Gardening] as the record to be updated.

2.4 Additional tools and configuration options

DataUpdater can either remove/clean the datasource (in case of a remote table, delete all records in the table) after the import operation has completed, or leave it untouched; this can be configured as needed.

ETL (extract, transform and load) options are available; in case a specific ETL is required which is not available as a configurable item, a customization can be developed according to customer requirements. An ETL are routinely utilized to convert and normalize data coming from different datasources and destined to a single ContactLab user database.

Post-operation actions (post-actions) can also be specified as a form of ETL to perform highly customized maintenance operations (see "10 DataExchange Post-Actions")

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

2.4.1 DataPoller option

Normally a DataUpdater will generate an error (and leave the User database locked) if the expected source file is not available at the time of the scheduled execution.

Starting with ContactLab platform release "2013-01-28" a new option (DataPoller) can be activated. As the name suggests when this option is configured, the DataUpdater will check for the existence of the expected source file repeatedly and as soon as a source file is available, it will start processing it if and only if a second file (a "semaphore") exists. This ensures DataUpdater will not start processing during a copy operation on the source file.

The semaphore file must be named <filename>.ready where <filename> is the source file to be processed. E.g. if the source file is named "testfile.csv" the semaphore must be named "testfile.csv.ready"; if the sourcefile is named "testfile.csv.gz" then the semaphore file must be named "testfile.csv.gz.ready".

The DataPoller option will also rename the semaphore file at specific processing checkpoints; this enables you to monitor the execution and/or diagnose most frequent problems programmatically.

A normal execution path will approximate the following description,, assuming DataPoller expects the source file to be named "testfile.csv":

- Customer generates file testfile.csv
- Customer generates a file named testfile.csv.ready
- DataPoller will notice testfile.csv.ready is existing and starts working
- Testfile.csv.ready is renamed testfile.csv.acquired
- DataPoller starts the DataExchange (Updater or Importer) and renames testfile.csv.acquired to testfile.csv.inprogress
- If the DataExchange module terminates successfully, it renames the semaphore to testfile.csv.done
- If the DataExchange module terminates unsuccessfully it renames the semaphore to testfile.csv.failed.

2.5 Execution and reporting options

A DataUpdater operation can be launched manually using the web UI (*Configure* → *dataexchange*) or scheduled to run periodically. In the latter case, the configuration must be initially setup (activated) by ContactLab; once periodic execution is activated, customer will be able to modify it in the web UI.

It is possible to request that executions are retried for a certain number of times before giving up and considering it an error.

It is possible to request that an error does not lock the User Database. Please consider the implications (your subsequent deliveries will operate on a possibly out of data database).

After the operation is concluded, an automated summary report on results will be sent via e-mail (optionally). Customers can autonomously configure *one* recipient for these summary reports. It is also possible to view the summary report's contents in the web UI, in the same section.


The same recipient will receive alerts on errors or warning if an operation was not completely successful; diagnostic log files can be download from the Web UI - please refer to section "10. Diagnostics messages" for more information on diagnostic messages and their meaning.

The web UI user account under which the DataUpdater is configured (the DataUpdater "owner") will also be able to view in real-time progress and notifications on DataUpdater operations. This is only available for the owner of the configuration. Every DataUpdater configuration has one and only one owner; it can be specified when requesting activation of this module.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

3. The DataDem module

The DataDem module allows creating customized filters (qualifiers) together with a user database from an external source.



The DataDem module requires a ContactLab user database as a target of its operations. The database must exist prior to the execution of the module, and it must include two mandatory fields, "DEM" and "flag_test". These fields (their name is fixed) are used to build the qualifier, or filter, for effective delivery (DEM) and test delivery (flag_test). DEM is automatically managed by ContactLab, while flag_test must be specified by the customer in the datasource (read further on).

3.1 Supported file formats and datasource structure

The DataDem *datasource* is a CSV (comma separated value) text file.

Fields in the CSV file must correspond exactly both in ordering and datatypes to fields defined in the destination ContactLab user database.

The field separator, string delimiter and line-ending characters can be configured according to customer needs.

An additional field (*flag_test*) must always be present; when the value of this field is "1", the record containing it will be marked to be included in the "test" qualifier for the campaign, used to automatically select the recipient list for test deliveries.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Example:

Let's suppose the destination user database includes the following fields for each recipient: EMAIL, CAMPAIGN_TYPE, FIRSTNAME, LASTNAME, ADDRESS, PHONE, SEX

Given the following datasource content, which includes the fields above specified, in the same order, and the additional mandatory *flag_test* as the last field in the row:

```
"jsmith@example.com";"Gardening";"John Smith";"Rossi";"1, Rome St.";09941444;"M";"1"\r\n
"tinaf@example.org";"Motors";"Tina";"Foo";" 3, Time Sq.";21199001;"F";"0"\r\n
"carly.f@clab1.net";"Gardening";"Carly";"Fines";"10, Ten St.";67710221;"F";"1"\r\n
```

When DataDem processes this sample datasource, it will load three recipients; two of these (John Smith and Carly Fines) will received test deliveries, as the *flag_test* field for them has the value "1"; while Tina Foo will not receive test deliveries.

In order to be processed the datasource CSV file must be named according to a strict naming convention:

`yyyyMMdd_<qualifier_name>_DELIVERY.csv`

where

- *yyyyMMdd* is the date in ISO format (year, month, day of the month) when the DataDem operations must take place¹
- *<qualifier_name>* is the name of the qualifier DataDem will automatically create in order to select recipient included in the datasource.
- *_DELIVERY.csv* is a constant string

The DataDem module will process the file on the date specified in the filename (*yyyyMMdd*). Moreover, even on the date specified, it will only actually consider it if a *semaphore file* is present with its name adhering to the strict naming convention:

`yyyyMMdd_<qualifier_name>_OK.txt`

The content of the semaphore file is not important; it can be an empty file; it must simply be named exactly as the datasource except for the final suffix (*_OK.txt* instead of *_DELIVERY.csv*).

As a practical example, in order to prepare a datasource for DataDem and have it processed on Aug 1st, 2010 to create a "SAMPLEFILTER" qualifier for a delivery, two files must be available in the source location (read further) with the following names:

`20100801_SAMPLEFILTER_DELIVERY.csv`

and the semaphore

`20100801_SAMPLEFILTER_OK.txt`

¹ In the current release of ContactLab, this date is relative to ContactLab's standard timezone (Europe/Paris, "CET")

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

3.2 Location of the datasource

Once the datasource (file or remote database) is available, DataDem must be able to access it in order to perform its duty. The following approaches are available for this step:

- **Source file available via FTP/SFTP:** Customer can provide ContactLab with access to a *secured and controlled* FTP or SFTP (the latter being strongly suggested) area provided specifically for this purpose. It is required specific credentials are used, dedicated to ContactLab. In case customer has difficulties providing an account with these characteristics, he/she can ask ContactLab to provide such an account on its own servers. ContactLab will provide credentials and instructions to connect to the customer-reserved area on its servers; customer will have to setup a process to upload the file(s) in this area.
- **Source file available via HTTP/HTTPS:** DataDem can also retrieve a named file from an http/https protected resource.

3.3 Operation modes

DataDem will process the datasource file by automatically calculating a value for the implied DEM field (it is a sequential integer value, incremented on each DataDem operation to ensure an unique value is attributed to every DataDem operation). All other fields are assigned values according to the content of the datasource – including the mandatory *flag_test* field.

Once all the recipients are loaded, two qualifiers (a delivery qualifier and a test qualifier) with the name specific in the datasource filename will be automatically created. ContactLab's customer will find them in the web UI. They can be easily identified as they adhere to a string naming convention:

- *<DEM>_<qualifier_name>* for the delivery qualifier
- *<DEM>_[TEST]_<qualifier_name>* for the test qualifier.

Where *<DEM>* is the id (automatically assigned) of the DataDem operation, and *[TEST]* is a constant (fixed) string.

Each DataDem operation creates a new delivery and qualifier referring to the automatically calculated DEM field value. Recipients are *appended* to any previous content of the table.

By default, 4 months after the operation, records with the same DEM value will be deleted all together. This allows automatic maintenance for the user database.

Occasionally, different scheduling for removals might be agreed in order to accommodate for controlled growth or the table or to satisfy specific customer requirements.

Example:

Let's suppose we have a customer recipient list needing the following fields:
EMAIL, CAMPAIGN_TYPE, FIRSTNAME, LASTNAME

A specially created user database in ContactLab will present the following fields:

EMAIL	CAMPAIGN_TYPE	FIRSTNAME	LASTNAME	FLAG_TEST	DEM
-------	---------------	-----------	----------	-----------	-----

(please notice the two mandatory additional fields *flag_test* and *DEM*).

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

In this example, our customer prepares two datasources.

The first datasource is named *20100801_FIRSTSAMPLE_DELIVERY.csv* and contains the following records/lines:

```
"jsmith@example.com";"Gardening";"John";"Smith";"1"\r\n
"tinaf@example.org";"Motors";"Tina";"Foo";"0"\r\n
"carly.f@clab1.net";"Gardening";"Carly";"Fines";"1"\r\n
```

And obviously the semaphore file named *20100801_FIRTSAMPLE_OK.txt* is created in the same place. The second datasource is named *20100802_SECONDSAMPLE_DELIVERY.csv* and it contains the following records/lines:

```
"tom.white@example.com";"Motors";"Tom";"White";"0"\r\n
"rb@example.net";"Motors";"Robert";"Bar";"0"\r\n
"jean.remi@example.com";"Gardening";"Jean";"Remi";"1"\r\n
```

Once again, the semaphore file is made available with the name *20100802_SECONDFILTER_OK.txt*. We further assume this is the first time DataDem runs for this customer.

On Aug 1st , 2010, DataDem will process the first datasource (*20100801_FIRSTSAMPLE_DELIVERY.csv*) and add the following records to the destination user database:

EMAIL	CAMPAIGN_TYPE	FIRSTNAME	LASTNAME	FLAG_TEST	DEM
Jsmith@example.com	Gardening	John	Smith	1	1
Tinaf@example.org	Motors	Tina	Foo	0	1
carly.f@clab1.net	Gardening	Carly	Fines	1	1

Please notice: fictitious data

On Aug 2nd, 2010 DataDem will process the second datasource (*20100802_SECONDSAMPLE_DELIVERY.csv*). After this processing, the content of the user database will be as follows:

EMAIL	CAMPAIGN_TYPE	FIRSTNAME	LASTNAME	FLAG_TEST	DEM
Jsmith@example.com	Gardening	John	Smith	1	1
Tinaf@example.org	Motors	Tina	Foo	0	1
carly.f@clab1.net	Gardening	Carly	Fines	1	1
Tom.white@example.com	Motors	Tom	White	0	2
Rb@example.net	Motors	Robert	Bar	0	2
Jean.remi@example.com	Gardening	Jean	Remi	1	2

Please notice: fictitious data.

Moreover, on Aug 1st 2010 two filters will be created: *1_FIRSTSAMPLE* selecting all recipients with the

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

DEM field valued "1"; *1_[TEST]_FIRSTSAMPLE* selecting all recipients with DEM field valued "1" and flag_test field valued "1" (John Smith and Carly Fines in our example).

And on the following day, two new qualifiers will be created: *1_SECONDSAMPLE* selecting all recipients with DEM field valued "2" and *1_[TEST]_SECONDSAMPLE*, selecting recipients with DEM valued "2" and flag_test valued "1".

Customer will be able to quickly prepare and send new deliveries basing on these automatically created qualifiers either with the web UI or the XML-RPC API.

3.4 Execution and reporting options

A DataDem operation can be launched manually using the web UI (*Configure* → *dataexchange*) or scheduled to run periodically. In the latter case, the configuration must be initially setup (activated) by ContactLab; once periodic execution is activated, customer will be able to modify it in the web UI, but it is possible to activate periodic execution from the web UI.

After the operation is concluded, an automated summary report on results will be sent via e-mail. Customer can autonomously configure *one* recipient for these summary reports. It is also possible to view the summary report's contents in the web UI, in the same section.

The same recipient will receive alerts on errors or warning if an operation was not completely successful; diagnostic log files can be download from the Web UI - please refer to section "11. Diagnostics messages" for more information on diagnostic messages and their meaning.


The web UI user account under which the DataUpdater is configured (the DataUpdater "owner") will also be able to view in real-time progress and notifications on DataImporter operations. This is only available for the owner of the configuration. Every DataUpdater configuration has one and only one owner; it can be specified when requesting activation of this module.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

4. The DataImporter module

The DataImporter module allows loading, in *append* or *refresh* mode, a recipient / user database in ContactLab with data generated from external sources.

IMPORTANT NOTICE. The DataUpdater module should always be preferred over DataImporter. DataImporter will not preserve primary keys when used in refresh mode, and will generate many duplicates of the same records when used in append mode. Please consider using DataUpdater instead of DataImporter whenever possible.



4.1 Supported file formats and datasource structure

The DataImporter module needs a *datasource* providing data to be applied to the user database for any operation. The datasource can be generated in various formats, but there must exist a clear relationship among the datasource's structure and the user database's field definitions in ContactLab.

The following formats are supported:

- **CSV (*comma separated value*) file:** fields in the CSV file must correspond exactly both in ordering and datatypes to fields defined in the destination ContactLab user database. The field separator, string delimiter and line-ending character can be configured according to customer needs.
- **XML file:** a single "root" node (dataroot) must include child nodes (RECORD) for every record, and every record will contain tags with name corresponding to the user databases' field names. Values in these tags will be applied to records being imported by the DataImporter module.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Example:

```
<?xml version="1.0" encoding="ISO-8859-1" ?>
  <dataroot>
    <RECORD>
      <EMAIL>Foo.Bar@example.com</EMAIL>
      <FIRSTNAME>Foo</FIRSTNAME>
      <LASTNAME>Bar</LASTNAME>
      <ADDRESS>via roma 123</ADDRESS>
      <PHONE>3291234567</PHONE>
      <SEX>m</SEX>
    </RECORD>
    <RECORD>
      ...
      ...
    </RECORD>
    ...
  </dataroot>
```

In this example, the destination user database will be composed of fields EMAIL, FIRSTNAME, LASTNAME, ADDRESS, PHONE, SEX; they will be populated with tag values taken from each record found in the XML file.

4.2 Location of the datasource

Once the datasource (file or remote database) is available, DataImporter must be able to access it in order to perform its duty. The following approaches are available for this step:

- **Source file available via FTP/SFTP/FTPS:** Customer can provide ContactLab with access to a *secured and controlled* FTP or SFTP (the latter being strongly suggested) area provided specifically for this purpose. It is required specific credentials are used, dedicated to ContactLab. In case customer has difficulties providing an account with these characteristics, he/she can ask ContactLab to provide such an account on its own servers. ContactLab will provide credentials and instructions to connect to the customer-reserved area on its servers; customer will have to setup a process to upload the file(s) in this area.
- **Source file available via HTTP/HTTPS:** DataImporter can also retrieve a named file from an http/https protected resource.
- **Source available as a remote database table:** if the remote database approach is chosen, customer will have to provide ContactLab with necessary info to perform a jdbc-supported connection to the remote database. He/she will also be responsible for any additional network setup and configuration which might be needed on customer's IS side to allow access from ContactLab's farm. ContactLab will test access during configuration; it will then give availability of the remote database for granted.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

As an option, in addition to using an encrypted transport such as SFTP or HTTPS, it is also possible to use PGP/GPG public/private key pair encryption. Customer will have to provide its public key to ContactLab and ContactLab will provide its public key to customer.

As an option, files can be compressed using one of the industry standard ZIP, BZIP2 and GZIP compression formats. ContactLab will decompress them "on the fly" before processing their content.

As an option, compression and PGP/GPG encryption can be applied at the same time (in the specified order) on DataExchange files.

As an option, the module can be configured to *rename* the source file by automatically adding a timestamp with format YYYYMMDDHHmmss or *remove* it.

4.3 Operation modes

Datalmporater is usually setup for a *full refresh* operation mode: every time a new datasource (file etc.) is available, it will *first* completely empty the destination user database, and then insert all records from the datasource.

It is also possible to configure the Datalmporater in *append* mode: in this configuration, the module will not wipe out all contents of the destination user database, but simply add records found in the datasource to previous content. In this configuration it is also possible to specify a "deletion filter" so that only records matching the filter will be deleted prior to appending the content of the datasource.

4.4 Limitations

If Datalmporater module is setup for a *full refresh* and the related User Database hosted in Contactlab doesn't have a customer managed Primary Key, the following problems may occur:

- Impossibility to aggregate events by user: since a unique id is not maintained, it's impossible to recognize user events (such as bounces, opens or views) of different deliveries.
- Newsletter online version may not work correctly and dynamic fields may not be available.

For these reasons, we **strongly recommend** to activate a DataUpdater instead of a Datalmporater module.

4.5 Additional tools and configuration options

Datalmporater can either remove/clean the datasource (in case of a remote table, delete all records in the table) after the import operation has completed, or leave it untouched; this can be configured as needed.

ETL (extract, transform and load) options are available; in case a specific ETL is required which is not available as a configurable item, a customization can be developed according to customer requirements. An ETL are routinely utilized to convert and normalize data coming from different datasources and destined to a single ContactLab user database.

Post-operation actions (post-actions) can also be specified as a form of ETL to perform highly customized maintenance operations (see "10. DataExchange Post-Actions")

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

4.5.1 DataPoller option

A DataImpoter will normally fail is the source file is not available at scheduled execution time. It is possible to configure the DataPoller option to instead have the process wait until the source file is available. Please refer to "2.4.1 DataPoller option" for a description of this option.

4.6 Execution and reporting options

A DataImporter operation can be launched manually using the web UI (*Configure* → *dataexchange*) or scheduled to run periodically. In the latter case, the configuration must be initially setup (activated) by ContactLab; once periodic execution is activated, customer will be able to modify it in the web UI.

After the operation is concluded, an automated summary report on results will be sent via e-mail (optionally). Customers can autonomously configure *one* recipient for these summary reports. It is also possible to view the summary report's contents in the web UI, in the same section.

The same recipient will receive alerts on errors or warning if an operation was not completely successful; diagnostic log files can be download from the Web UI - please refer to section "11. Diagnostics messages" for more information on diagnostic messages and their meaning.


The web UI user account under which the DataImporter is configured (the DataImporter "owner") will also be able to view in real-time progress and notifications on DataImporter operations. This is only available for the owner of the configuration. Every DataImporter configuration has one and only one owner; it can be specified when requesting activation of this module.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

5. The DataCollector module

The DataCollector module allows merging data from multiple text files and then trigger the execution of a DataExchange module.

This is required when you need to feed a dataUpdater or a dataImporter with datasource available on multiple files.



5.1 Supported file formats and datasource structure

The DataCollector module needs one or more CSV (comma separated value) files as *datasource*.

The module can be configured to process and merge data provided in a specific order, based on files attributes or custom rules.

The output file must be a valid datasource for the DataExchange module triggered after each DataCollector execution (See related documentation for details).

As an option, CSV first line of specific datasource files can be removed from the output.

5.2 Access and location of the datasource

DataCollector searches for all files matching a specific regular expression inside a given directory and use them as datasource.

Once the datasource is available, DataCollector must be able to access it via FTP/SFTP/FTPS: Customer can provide ContactLab with access to a *secured and controlled* FTP or SFTP (the latter being strongly

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

suggested) area provided specifically for this purpose. It is required specific credentials are used, dedicated to ContactLab. In case customer has difficulties providing an account with these characteristics, he/she can ask ContactLab to provide such an account on its own servers. ContactLab will provide credentials and instructions to connect to the customer-reserved area on its servers; customer will have to setup a process to upload the file(s) in this area.

As an option, the module can be configured to *rename* source files by automatically adding a timestamp with format YYYYMMDDHHmmss or *remove* them.

As an option, the module can be configured to *rename* output file by automatically adding a timestamp with format YYYYMMDDHHmmss.

As an option, the output file can be compressed using one of the industry standard ZIP, BZIP2 and GZIP compression formats.

5.3 Additional tools and configuration options

DataCollector can either remove/clean the datasource after the merge operation has completed, or leave it untouched; this can be configured as needed.

After its execution, DataCollector can trigger the execution of another DataExchange module.

5.4 Execution and reporting options

A DataCollector operation can be launched manually using the web UI (*Configure* → *dataexchange*) or scheduled to run periodically. In the latter case, the configuration must be initially setup (activated) by ContactLab; once periodic execution is activated, customer will be able to modify it in the web UI.

After the operation is concluded, an automated summary report on results will be sent via e-mail (optionally). Customers can autonomously configure *one* recipient for these summary reports. It is also possible to view the summary report's contents in the web UI, in the same section.


The same recipient will receive alerts on errors or warning if an operation was not completely successful; diagnostic log files can be download from the Web UI - please refer to section "11. Diagnostics messages" for more information on diagnostic messages and their meaning.

The web UI user account under which the DataCollector is configured (the DataCollector "owner") will also be able to view in real-time progress and notifications on DataCollector operations. This is only available for the owner of the configuration. Every DataCollector configuration has one and only one owner; it can be specified when requesting activation of this module.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

6. The DataExporter module

While DataUpdater, DataDem and DataImporter deal with transferring data *to* ContactLab from external sources, the DataExporter allows to export data *from* ContactLab to a customer repository.



With DataExporter, ContactLab customers gain access to data about two important indicators for campaigns: campaign-level aggregated feedback statistics, and recipient-level details for feedback events. Detailed info on available feedback indicators are available in this section.

Since early 2017, recipient-level details and campaign-level aggregations are generated continuously, with an estimated maximum delay of 30 minutes between event registration and data availability for exporting.

6.1 Supported file formats

DataExporter can generate datasets in the following formats:

- **CSV file:** a standard comma-separated-value with a header line (the first line in the files will contain the names of the fields). Field separator, string delimiter and line terminator characters can be configured according to customer needs. Also, the generated file name can be specified by the customer.
- **XML file:** files will include a single "root" node called ROOT with multiple child nodes (RECORDELEMENT) for every record.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

6.2 Location of the destination

ContactLab can provide DataExporter results (datasets) delivering them to one of the following destinations:

- **Upload or download with FTP/SFTP/FTPS:** Customer can provide ContactLab with access to a *secured and controlled* FTP or SFTP (the latter being strongly suggested) area provided specifically for this purpose. It is required specific credentials are used, dedicated to ContactLab. In case customer has difficulties providing an account with this characteristics, he/she can ask ContactLab to provide such an account on its own servers. ContactLab will provide credentials and instructions to connect to the customer-reserved area on its servers; customer will have to setup a process to upload the file(s) in this area.
- **Upload via Axway CFT.** Option available on request.

As an option, in addition to using an encrypted transport such as SFTP or HTTPS, it is also possible to use PGP/GPG public/private key pair encryption. Customer will have to provide its public key to ContactLab and ContactLab will provide its public key to customer.

As an option, files can be compressed using one of the industry standard ZIP, BZIP2 and GZIP compression formats.

As an option, compression and PGP/GPG encryption can be applied at the same time (in the specified order).

6.3 Operations mode and available information

The preparation of the feedback dataset can be "full" or "incremental". If "full", *all* existing data in ContactLab will be exported every time; if "incremental", DataExporter keeps track of the last export operations timestamp and exports all data generated or modified *after* the last operation.

Please be aware that, in case of a remote database as destination location, a "full" export will first delete every record in the destination table.

The "full" setup is available but only suggested for small datasets (small number of total messages sent in a typical monthly period) and/or to temporarily activate a feedback export while the "incremental" setup is fine-tuned. Although no specific limit is imposed on the amount of data, if the customer expects to use the "full" export for more than six months, special dispositions must be agreed with ContactLab at setup time.

There are three different datasets available for DataExporter. Customer can choose which are interesting to his/her needs. Also, each dataset has different fields available. Once again, customer can choose which fields are to be exported for each dataset.

Delivery dataset: aggregated campaign (delivery)-level key performance indicator. The following table summarizes available indicators (fields in the dataset). Starting with ContactLab Release "2014-01-27" it is possible to request a different ordering of fields at DataExporter configuration time.

Field	Description	Type	Format
delivery_id	Unique id for delivery	Numeric	
newsletter	Name of newsletter/group used in delivery	Alphanumeric	Variable-length string (255 max)
subject	Delivery subject	Alphanumeric	Variable-length string (255 max)
start_date	Date and time of start of delivery	ISO-format timestamp	yyyy-MM-dd hh:mm:ss
recipients	Total number of recipients	Numeric	
description	Qualifier/filter descriptive name	Alphanumeric	Variable-length string (255 max)

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

newsletter_id	group/newsletter id	Numeric	
userdb_id	user database unique id	Numeric	
charset	Id of charset used	Alphanumeric	Variable-length string (255 max)
role	"role" of delivery in a multi-segment delivery (e.g. split delivery, A/B testing)	Numeric	0: non-segmented; 1: master of segmented; 2: master for A/B test; 101-199 segment; 200 "winner" segment of A/B test
parent_id	Id of "master" in multi-segment delivery	Numeric	
medium²	Delivery medium/channel type	Numeric	0: email, 1: sms, 2: fax, 3: push
title	Delivery title in Contactlab	Alphanumeric	Variable-length string (255 max)
category_id	Id of "master" in multi-segment delivery	Numeric	
qualifier_id	Id if qualifier/filter	Numeric	
end_date	Date and time of start of delivery	ISO-format timestamp	yyyy-MM-dd hh:mm:ss
mail_from	RFC5322 From ("Friendly From")	Alphanumeric	Variable-length string (255)
reply_to	RFC 5322 Reply-To header value	Alphanumeric	Variable-length string (255)
schedule_date	Date and time of scheduling (if any)	ISO-format timestamp, or empty	yyyy-MM-dd hh:mm:ss or empty
remove_duplicates	Flag:remove duplicate addresses from broadcast queue	Numeric	0 or 1
is_test	Flag: "Test" delivery	Numeric	0 or 1
track_urls	Flag: click tracking enabled	Numeric	0 or 1
read_stats	Flag: open/view tracking enabled	Numeric	0 or 1
communication_category_id	Communication Category Id	Numeric	1 or 6

The *role* and *parent_id* fields are meaningful for multi-segment deliveries only, e.g. "split deliveries" or "A/B testing" deliveries. These deliveries are managed by setting up a "master" delivery acting as a container/parent for all segments. When a record is referring to a segment of a multi-segment delivery, the *role* field will have a value between 101 and 199 and *parent_id* will contain the *delivery_id* of the master delivery. When a record is referring to the master delivery, the *role* field will be valued 1. For non-segmented deliveries, the *role* field will be set to 0 (zero).

The *category_id* field will specify the Category of the delivery as assigned by the user in the Web UI. If you are interested in this feature, please ask our Customer Care for the current list of allowed categories (as seen in the web UI) and their numerical ids.

The *communication_category_id* reports the "Communication Category" introduced in ContactLab Release "2013-04-08". Currently supported communication categories are 1 (Marketing/Bulk) and 6 (Transactional).

² Available starting with Release 2011-07-18. DataExporter configurations set up prior to this release require reconfiguration.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Delivery_info dataset: specifically for delivery notes/labels (key-value pairs customer can attach to any delivery, usually utilized to classify deliveries to enable integration in external customer applications)

Field	Description	Type	Format
delivery_info_id	Unique id for this record	Numeric	
delivery_id	Unique id for delivery	Numeric	
label	Label/note descriptive text (key)	Alphanumeric	Variable-length string (255 max)
value	Label/note text value (value)	Alphanumeric	Variable-length string (255 max)
is_system	Flag: this is a system key	Alphanumeric	Variable-length string (255 max)

Event_info dataset: detailed information on all recipients' actions (*events*) tracked for a delivery.

Field	Description	Type	Format
delivery_id	Unique delivery (campaign) id	Numeric	
event_id	Unique delivery id	Numeric	
event_code	Event code	Character	Single Character
event_details	Event detail	Alphanumeric	Variable-length string (255)
event_subdetails	Event subdetail	Alphanumeric	Variable-length string (255 max)
category_id	Event category id	Numeric	
category_desc	Event category description	Alphanumeric	Variable-length string (255)
event_date	Event date and time	ISO-format timestamp	yyyy-MM-dd hh:mm:ss
user_pk	Primary key of recipient in user database	Numeric	
ip_address	IPv4 address of host generating event	dotted-quad	Variable-length string (16)
user_agent	User agent signature	Alphanumeric	Variable-length string (255)

The *event_code* can assume one of the following values (please notice the character code is **case sensitive** – event code "s" has a different meaning than event code "S"):

- A: an abuse complaint was filed by recipient using the form referenced in the X-Abuse header
- B: "bounce" event (a bounce was received when trying to deliver the message)
- C : "click" event (a tracked link was clicked)
- D: an abuse complaint was filed by recipient in a non-structured way (e.g. mail to abuse contact, general-purpose abuse complaint form...)
- E: "error" event (email address was invalid or other causes)
- F: feedback loop, recipient filed a complaint via a feedback loop feed
- I (uppercase i): Delivery was interrupted, so this message was not sent.
- J: temporary blacklist match: message was NOT sent because recipient was found in temporary blacklist
- K: permanent blacklist match: message was NOT sent because recipient was found in a

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

- permanent blacklist (including Robinson Lists)
- L: list-unsubscribe, recipient asked for unsubscription via List-Unsubscribe header automation
- m: profile update, available if events of this type are configured to be tracked
- o: optout (unsubscribe), available if events of this type are configured to be tracked (requires ContactLab's integrated Subscription System).
- s: optin (subscribe), available if events of this type are configured to be tracked (requires ContactLab's integrated Subscription System)
- S: "sent" event for non-triggered email message
- T: "sent" event for a triggered email message or for a ContactLab Smart Relay managed message³
- V: "view" or "open" event (the open/view tracker marker URL was seen by ContactLab)
- X: recipient entered the blacklist/suppression list because of a non-delivery-related event⁴.
- Y: recipient entered the temporary blacklist/suppression list as a result of an event
- Z: recipient entered the permanent blacklist/suppression list⁵. This is the fourth consecutive bounce or any "bad destination mailbox address" bounce. It replaces the previous 'X' event

Event_id is the primary key for events: it is unique for events for a given customer account, even across different user databases for the same customer. Together with *event_date*, *event_code* and *event_details*, it will always have a value.

Ip address and *user agent* instead are filled when available (when the event is caused by a user action from an Internet-connected device). The *event_details*, *event_subdetails*, *category_id* and *category_desc* fields can assume different meanings according to the event code.

The DataExporter standard configuration will export *all* available information (event records for all event codes). As an optional configuration, events can be filtered by ContactLab before the exporter stream is generated in order to include events the customer is interested in.

Custom filters on events to be exported can be requested to your Account/Sales manager and will be estimated as custom development work.

Event details will show some difference according to the *medium* of the campaign. Let's examine all available choices to simplify matters.

6.3.1 Event info details for email messages

The following table summarizes the combinations:

Event Code	Event Details	Event Subdetails	Category Id	Category Desc	Ip Address	User Agent	Recipient (*)
A	Reason – free text, entered by	Recipient Email domain	—	—	Origin IP address	User-agent header of	v

³ In a future release a separate event code will be used for SmartRelay send events.

⁴ In the current release of ContactLab, the following cause will not generate an 'X' event:

- carry-over of blacklist entries because of a "shared" blacklist setup

This limitation will be resolved in a future release of ContactLab.

⁵ J, Y and Z were added in ContactLab Release "2011-12-12" following the introduction of the temporary suppression engine.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

	user				of http req.	http req.	
B	Short description of bounce	Bounce class: hard (H), soft (S)	Bounce category code	—	—	—	v
C	Tracked link destination URL	Link descr. as set up in ContactLab UI	Link category id	Link category name	Origin IP address of http req.	User-agent header of http req.	v
D	Complainant email address	—	—	Notes	—	—	v
E	Recipient email address	—	—	—	—	—	v
F	—	Recipient email domain	—	—	—	—	v
I	Recipient email address	Recipient email domain	—	—	—	—	v
J	Recipient email address	—	—	—	—	—	v
K	Recipient email address	Blacklist id	Blacklist category	—	—	—	v
L	—	Recipient email domain	—	—	Origin IP address of http req.	User-agent header of http req.	v
m	Recipient email address	—	—	—	Origin IP address of http req.	User-agent header of http req.	v
o	Recipient email address	Subscription form id	—	—	Origin IP address of http req.	User-agent header of http req.	v
s	Recipient email address	—	—	—	Origin IP address of http req.	User-agent header of http req.	v
S	Recipient email address	Recipient email domain	—	—	—	—	v
T	Recipient email address	Recipient email domain	— ⁶	— ⁷	—	—	v
V	Webmail type	—	—	Device identification data	Origin IP address of http req.	User-agent header of http req.	v
X	Recipient email address	Recipient email domain	Reason code	—	—	—	v

⁶ For SmartRelay send events, this field can be populated by customer using custom header in the message as an optional feature.

⁷ For SmartRelay send events, this field can be populated by customer using custom header in the message as an optional feature.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Y	Recipient email address	Number of consecutive bounces	Reason code	Blacklisted until timestamp	—	—	v
Z	Recipient email address	Number of consecutive bounces	Reason code	—	—	—	v

(*) Recipient field. This field is available as an optional configuration and will always contain the Recipient email address. This enhancement was implemented to simplify exported events ingestion at customer end. In order to guarantee backward compatibility, the same information will still be inserted in the "Event Details" field as reported in the above table, so that existing ingestion procedure will still work as expected.

6.3.2 Event info details for SMS messages

SMS messages support the following event codes:

- B: "bounce" event - a negative Delivery Report (DR) notification was received when trying to deliver the message. We are currently reporting the verbatim description and code from the operator, which do not have a standard classification.
- D: an abuse complaint was filed by recipient in a non-structured way
- E: "error" event (phone number was invalid or other causes)
- I (uppercase i): Delivery was interrupted, so this message was not sent.
- S: "sent" event for non-triggered SMS message
- T: "sent" event for a triggered SMS message or for a ContactLab Smart Relay managed message⁸
- V: for SMS messages, this represents a positive Delivery Report (DR) notification received for this message.

Please be aware that currently we do not support blacklist functionality for SMS message. In a future release we will classify DR codes and introduce the blacklist functionality. This means the J, X, Y, and Z event codes will never actually be found in a DataExporter feed for SMS messages; we however suggest to consider them in your import procedures as a no-op to prepare for future upgrades.

The following table summarizes the combinations (including the I,J,X and Y events):

Event Code	Event Details	Event Subdetails	Category Id	Category Desc	Ip Address	User Agent	Recipient
B	Short description of bounce	Bounce class: hard (H), soft (S)	Bounce category code	—	—	—	v
D	Complainant MSISDN	—	—	Notes	—	—	v
E	Recipient MSISDN	—	—	—	—	—	v
I	Recipient MSISDN	—	—	—	—	—	v

⁸ In a future release a separate event code will be used for SmartRelay send events.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

S	Recipient MSISDN	—	—	—	—	—	√
T	Recipient MSISDN	—	— ⁹	— ¹⁰	—	—	√
V	—	—	—	—	—	—	√

6.3.3 Event info details for Push Notification messages

Push Notification messages support the following event codes:

- B: "bounce" event – the message was not accepted when delivery was attempted
- D: an abuse complaint was filed by recipient in a non-structured way
- C : "click" event (a tracked link was clicked)
- E: "error" event (device token, or equivalent, was invalid or other causes)
- I (uppercase i): Delivery was interrupted, so this message was not sent.
- K: permanent blacklist match: message was NOT sent because recipient was found in a permanent blacklist (including Robinson Lists)
- S: "sent" event for a non-triggered Push Notification message
- T: "sent" event for a triggered Push Notification message or for a ContactLab Smart Relay managed message¹¹
- V: "view" event for a tracked message
- X: recipient entered the blacklist/suppression list because of a non-delivery-related event¹².

The following table summarizes the combinations:

Event Code	Event Details	Event Subdetails	Category Id	Category Desc	Ip Address	User Agent	Recipient
B	—	Bounce class: hard (H), soft (S)	Bounce category code	—	—	—	√
C	Tracked link destination URL	Link descr. as set up in ContactLab UI	Link category id	Link category name	Origin IP address of http req.	User-agent header of http req.	√
D	—	—	—	Notes	—	—	√
E	Recipient device id	—	—	—	—	—	√
I	Recipient device id	Recipient email domain	—	—	—	—	√
S	Recipient email address	Recipient email domain	—	—	—	—	√

⁹ For SmartRelay send events, this field can be populated by customer using custom header in the message as an optional feature.

¹⁰ For SmartRelay send events, this field can be populated by customer using custom header in the message as an optional feature.

¹¹ In a future release a separate event code will be used for SmartRelay send events.

¹² In the current release of ContactLab, the following cause will not generate an 'X' event:

- carry-over of blacklist entries because of a "shared" blacklist setup

This limitation will be resolved in a future release of ContactLab.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

T	Recipient email address	Recipient email domain	___ ¹³	___ ¹⁴	—	—	√
V	Webmail type	—	—	Device identification data	Origin IP address of http req.	User-agent header of http req.	√
X	Recipient email address	Recipient email domain	Reason code	—	—	—	√

For B (bounce) codes ContactLab aggregates provider-specific codes into three categories:

- 3001 for temporary errors (e.g. "GCM temporarily unavailable", "APN processing error")
- 3002 for final, recipient-specific errors (e.g. "GCM invalid registration", "APN missing device token")
- 3003 for final, message-specific errors (e.g. "GCM message too big", "APN missing topic")

6.3.4 Device Identification Data for "view" (V) events

Starting with ContactLab platform release "2013-01-28", the "Category Desc" field for event type "V" (view) is populated with device identification data from the ScientiaMobile WURFL device detection database.¹⁵

To minimize inconveniences to our customers, any DataExporter configuration already existing at the time of the release will *not* have the "Category Desc" field populated with device detection data.

If you are interested in receiving these data please ask our Customer Care to enable it on your DataExporter configuration, but please check that this is not going to break your import procedures before asking for it.

All configurations created after the release date will find this field populated.

To ease automated parsing of these data, subfields for the device identification are concatenated with character "~" (tilde) as a field separator.

Subfields are provided in the following order:

- ContactLab internal brand/vendor id (an integer number)
- Brand/vendor "human readable" name
- ContactLab internal model id (an integer number)
- Device Model "human readable" name
- Device Model "marketing" name
- Mobile device flag (1 if device is mobile, 0 otherwise)
- Tablet device flag (1 if device is a tablet, 0 otherwise)
- Operating System name

¹³ For SmartRelay send events, this field can be populated by customer using custom header in the message as an optional feature.

¹⁴ For SmartRelay send events, this field can be populated by customer using custom header in the message as an optional feature.

¹⁵ ContactLab is a licensed early adopter of ScientiaMobile WURFL products. ContactLab license covers usage of WURFL-derived data inside our platform, but you can also use these information to generate custom reporting outside of ContactLab platform, as long as you are an active customer of ContactLab. If you are interested in ScientiaMobile products to extend this license just ask us and we'll provide a contact..

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

- Operating System version
- Browser name
- Browser version

When a subfield value is not available it will be left empty so you can use a positional index to access subfields after separating them.

A few real-world samples:

```
6~Apple~5091~iPad~1~1~iPhone OS~6.0~Safari~
59~Microsoft~2~Internet Explorer~0~0~MSIE~7.0
16~Google~6573~Chrome~0~0~Desktop~0~23.0
14~Samsung~4517~GT-I9000~Galaxy S~1~0~Android~2.3~Android Webkit~
```

The following data is provided when the device was not correctly identified:

```
1~generic web browser~1~0~0~
```

6.3.5 Blacklist identification data in 'blacklist match' (K) events

Starting with Release 2013-04-08, the 'blacklist match' (K) event, which records all messages not sent because the recipient was in a supported permanent blacklist/suppression list at the time the campaign was processed, will provide additional info on *which* blacklist/suppression list matched.

Field 'Category id' will have a value according to the following:

- 101 if there was a match in ContactLab per-customer blacklist/suppression list
- 102 if there was a match in a Robinson List¹⁶
- 103 if there was a match in a custom suppression list¹⁷

When 'Category id' is either 102 or 103, field 'Event subdetails' will have a value according to the following:

- No value
- Unique id of the Robinson List/custom suppression list.

Currently supported Robinson List unique ids are:

1,2, or 3: Spanish "Listas Robinson" (www.listarobinson.es)

6.4 XML file format specifications

6.4.1 Delivery Dataset

```
<?xml version="1.0" encoding="UTF-8"?>
<ROOT>
  <RECORDELEMENT>
    <DELIVERY_ID>3034</DELIVERY_ID>
```

¹⁶ As of Release 2013-04-08, support for Spain's national "Listas Robinson" (listarobinson.es) has been introduced. More will follow.

¹⁷ Custom suppression lists will be introduced in a future release.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

```

    <NEWSLETTER>A sample mail</NEWSLETTER>
    <SUBJECT><![CDATA[A sample mail]]></SUBJECT>
    <START_DATE/>
    <RECIPIENTS>14</RECIPIENTS>
    <DESCRIPTION><![CDATA[Test join]]></DESCRIPTION>
    <CATEGORY_ID>0</CATEGORY_ID>
  </RECORDELEMENT>
</RECORDELEMENT>
  ...
</RECORDELEMENT>
  ...
</ROOT>

```

6.4.2 Delivery Info Dataset

```

<?xml version="1.0" encoding="UTF-8"?>
<ROOT>
  <RECORDELEMENT>
    <DELIVERY_INFO_ID>1</DELIVERY_INFO_ID>
    <DELIVERY_ID>26</DELIVERY_ID>
    <LABEL>label1</LABEL>
    <VALUE>test label</VALUE>
    <IS_SYSTEM>>false</IS_SYSTEM>
  </RECORDELEMENT>
</ROOT>

```

6.4.3 Event Info Dataset

```

<ROOT>
  <RECORDELEMENT>
    <DELIVERY_ID>1357</DELIVERY_ID>
    <NEWSLETTER><![CDATA[Newsletter Email Group]]></NEWSLETTER>
    <SUBJECT><![CDATA[New offers for you]]></SUBJECT>
    <START_DATE>2013-11-19 12:42:20.0</START_DATE>
    <RECIPIENTS>205891</RECIPIENTS>
    <DESCRIPTION><![CDATA[Qualifier or Filter Description]]></DESCRIPTION>
    <NEWSLETTER_ID>17</NEWSLETTER_ID>
    <USERDB_ID>17</USERDB_ID>
    <ROLE>0</ROLE>
    <PARENT_ID></PARENT_ID>
    <MEDIUM>0</MEDIUM>
    <TITLE></TITLE>
    <CATEGORY_ID>0</CATEGORY_ID>
    <QUALIFIER_ID>10</QUALIFIER_ID>
    <END_DATE>2013-11-19 12:48:42</END_DATE>
    <MAIL_FROM><![CDATA[New offers <offers@contactlab.com>]]></MAIL_FROM>
    <REPLY_TO><![CDATA[offers@contactlab.com]]></REPLY_TO>
    <SCHEDULE_DATE></SCHEDULE_DATE>
    <REMOVE_DUPLICATES>1</REMOVE_DUPLICATES>
    <IS_TEST>0</IS_TEST>
    <TRACK_URLS>1</TRACK_URLS>
    <READ_STATS>1</READ_STATS>
    <COMMUNICATION_CATEGORY_ID></COMMUNICATION_CATEGORY_ID>
  </RECORDELEMENT>

```

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

```

    <RECORDELEMENT>
...
    </RECORDELEMENT>
...
</ROOT>

```

6.5 Execution and reporting options

A DataExporter operation can be launched manually using the web UI (*Configure* → *dataexchange*) or scheduled to run periodically. In the latter case, the configuration must be initially setup (activated) by ContactLab; once periodic execution is activated, customer will be able to modify it in the web UI, but it is not possible to activate periodic execution from the web UI.

After the operation is concluded, an automated summary report on results will be sent via e-mail (optionally). Customers can autonomously configure *one* recipient for these summary reports. It is also possible to view the summary report's contents in the web UI, in the same section.

The same recipient will receive alerts on errors or warning if an operation was not completely successful; diagnostic log files can be download from the Web UI - please refer to section "10. Diagnostics messages" for more information on diagnostic messages and their meaning.

The web UI user account under which the DataExporter is configured (the DataExporter "owner") will also be able to view in real-time progress and notifications on DataExporter operations. This is only available for the owner of the configuration. Every DataExporter configuration has one and only one owner; it can be specified when requesting activation of this module.

6.6 Data subject to variation over time

Some of the data exported by the DataExporter can possibly be modified by user actions after it has been exported. Obviously, delivery statistics can change if recipients act after a period of time. This should be considered carefully when justifying decisions basing on data aggregated too "early".

Also, customer can perform actions in ContactLab which might change data used to identify some of the values in the available datasets (lookup fields).


For instance, if a customer deletes a delivery in ContactLab, all related event and campaign-level info will not be available anymore. Likewise, modifying link categories and their descriptions will immediately be reflected in subsequent exports, even though they might refer to events (e.g. clicks) happened before the modification took place. So in case of a full export, previously classified events might change their classification and assume new ones.

Please consult our CustomerCare or your Account whenever you have doubts with regard a DataExporter configuration, and/or you have unusual needs for data historical consistency.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

7. The DataDisplacer module

The DataDisplacer module allows exporting a recipient / user database in ContactLab to a remote system.



7.1 Supported file formats and destination structure

The DataDisplacer module allows extracting the contents of a User Database in ContactLab. This might be needed to re-sync the source if some data (e.g. unsubscribe markers) are updated only in Contactlab and needs to be transferred to customer. Or, a custom form might be implemented to modify user profile info in ContactLab, so customer would like to have its master database updated regularly with updated profile info. The name DataDisplacer has been chosen to avoid confusion with the DataExporter, but by all means, it is an export operation indeed. DataExporter exports events data, while DataDisplacer exports User Databases.

The following destination formats are supported:

- **CSV (comma separated value) file**: fields in the CSV file will correspond both in ordering and datatypes to fields defined in the destination ContactLab user database. The field separator, string delimiter and line-ending character can be configured according to customer needs.
- **XML file**: a single "root" node (dataroot) must will child nodes (RECORD) for every record, and every record will contain tags with name corresponding the user databases' field names. Values

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

in these tags will be applied to records being imported by the DataImporter module.

Example:

```
<?xml version="1.0" encoding="UTF-8"?>
<ROOT>
  <RECORDELEMENT>
    <EMAIL>someone.outthere@contactlab.com</EMAIL>
    <FIRSTNAME/>
    <LASTNAME/>
    <__cls1>0</__cls1>
  </RECORDELEMENT>
  <RECORDELEMENT>
    <EMAIL>same.chap@tomatointeractive.it</EMAIL>
    <FIRSTNAME/>
    <LASTNAME/>
    <__cls1>1</__cls1>
  </RECORDELEMENT>
  <RECORDELEMENT>
    <EMAIL>XtleZebW@contactlab.com</EMAIL>
    <FIRSTNAME>SlZDtOSR</FIRSTNAME>
    <LASTNAME>yjkoRMN4ag</LASTNAME>
    <__cls1>5000</__cls1>
  </RECORDELEMENT>
  ...
</ROOT>
```

In this example, the User Database is composed of fields EMAIL, FIRSTNAME, and LASTNAME; they will be populated with tag values taken from each record found in the XML file. __cls1 is a special field managed by ContactLab's integrated Subscription System.

- **Another ContactLab User DB:** it is possible to create a direct link to a second User DB in ContactLab. Please contact ContactLab's Customer Care or your dedicated Account to complete preparations for this setup, which requires the engagement of our Professional Services.

7.2 Location of the destination

ContactLab can deliver DataDisplacer results (exported datasets) delivering them to one of the following destinations:

- **Upload or download with FTP/SFTP/FTPS:** Customer can provide ContactLab with access to a *secured and controlled* FTP or SFTP (the latter being strongly suggested) area provided specifically for this purpose. It is required specific credentials are used, dedicated to ContactLab. In case customer has difficulties providing an account with this characteristics, he/she can ask ContactLab to provide such an account on its own servers. ContactLab will provide credentials and instructions to connect to the customer-reserved area on its servers; customer will have to setup a process to upload the file(s) in this area.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

As an option, in addition to using an encrypted transport such as SFTP or HTTPS, it is also possible to use PGP/GPG public/private key pair encryption. Customer will have to provide its public key to ContactLab and ContactLab will provide its public key to customer.

As an option, files can be compressed using one of the industry standard ZIP, BZIP2 and GZIP compression formats.

As an option, compression and PGP/GPG encryption can be applied at the same time (in the specified order).

7.3 Operation modes

When working with a remote database table, DataDisplacer is usually setup in *full refresh* operation mode: every time it is ready to export a User Database, it will *first* completely empty the destination user database/table, and then insert all records. It is also possible to configure *append* mode: in this configuration, the module will not wipe out all contents of the destination user database, but simply add records found in the User Database to previous content.

It is possible to specify a filter when exporting, so that not all contents of the User Database are exported but only those rows satisfying a filtering condition.

7.4 Additional tools and configuration options

ETL (extract, transform and load) options are available; in case a specific ETL is required which is not available as a configurable item, a customization can be developed according to customer requirements. Post-operation actions can also be specified to perform highly customized maintenance operations.

7.5 Execution and reporting options

A DataDisplacer operation can be launched manually using the web UI (*Configure* → *dataexchange*) or scheduled to run periodically. In the latter case, the configuration must be initially setup (activated) by ContactLab; once periodic execution is activated, customer will be able to modify it in the web UI.

After the operation is concluded, an automated summary report on results will be sent via e-mail (optionally). Customers can autonomously configure *one* recipient for these summary reports. It is also possible to view the summary report's contents in the web UI, in the same section.

The same recipient will receive alerts on errors or warning if an operation was not completely successful; diagnostic log files can be download from the Web UI - please refer to section "11. Diagnostics messages" for more information on diagnostic messages and their meaning.

The web UI user account under which the DataDisplacer is configured (the DataDisplacer "owner") will also be able to view in real-time progress and notifications on operations. This is only available for the owner of the configuration. Every DataDisplacer configuration has one and only one owner; it can be specified when requesting activation of this module.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

8. Managing DataExchange modules in ContactLab UI

DataExchange modules can be configured and managed using ContactLab web UI. By navigating to Configure → *dataexchange* a properly authorized user has access to two sections: Configuration (“Available and Active modules”) and log/planning with two tabs (“Available Modules” and “List of items planned or executing”).

The first section, “Available and active modules”:

Module identifies the activated module type (DataImporter, DataExporter, DataUpdater...), *Configuration* is a description useful to quickly identify a specific configuration when a large number of modules is active.

In the leftmost field, a *play* icon is shown when the module configuration in the same line will only be executed on demand (i.e. explicitly invoked by user through the web UI). If the icon in the bottom-right corner is a *pause icon* instead, periodic/scheduled execution is configured, and it is possible to suspend it by clicking that icon.

For on-demand modules, execution can be invoked from this same tab by clicking the play icon with a green arrow in its bottom right corner as show in the following picture.

CONFIGURE

DataExchange®

In this section, you can see the currently configured DataExchange® modules and activate them
It is possible to enter more than one request, which will be executed one at a time in order of insertion.

To request information or activate a DataExchange form, please contact ContactLab staff.

Available and active modules

ID	module	configuration	status	Schedule	
343	data-exchange.importer	Importazione utenti di sistema (db #117)	Enabled	everyday at 8:30 related to the time zone: Europe/Rome Last executed on: 09-09-2013 08:30 Next execution on: 10-09-2013 08:30	
475	data-exchange.importer	E-mail Marketing Consumer Report 2008 - IT - Italia (db #138)	Enabled	everyday at 8:00 related to the time zone: Europe/Rome Last executed on: 09-09-2013 08:00 Next execution on: 10-09-2013 08:00	
665	data-exchange.importer	E-mail Marketing Consumer Report 2009 - ES - Spagna (db #149)	Enabled	everyday at 5:00 related to the time zone: Europe/Rome Last executed on: 09-09-2013 05:00 Next execution on: 10-09-2013 05:00	

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

For periodic / scheduled execution configurations (play icon) clicking on the icon will activate the scheduling configuration form:

my contactlab configure create communicate analyse support

user db email groups sms groups fax groups virtual groups link categories dataexchange® integrations report delivery on-demand xml delivery

You are in: configure > dataexchange® company: ContactLab Srl

DataExchange®

The scheduling of a dataexchange can be modified in this section

data-exchange.importer :: Importazione utenti di sistema

 Current schedule: **everyday at 8:30 from 27/02/2012 13:03 related to the time zone: Europe/Rome**
 Last executed on: 09-09-2013 08:30 CEST (GMT +02:00)
 Next execution on: 10-09-2013 08:30 CEST (GMT +02:00)

minutes	hours	days	months	day of the week
30	<input type="radio"/> every hour <input checked="" type="radio"/> choose	<input checked="" type="radio"/> everyday <input type="radio"/> choose	<input checked="" type="radio"/> every month <input type="radio"/> choose	<input checked="" type="radio"/> every weekday <input type="radio"/> choose
	<div style="border: 1px solid #ccc; padding: 2px;"> 03 ▲ 04 05 06 07 08 ▼ </div>	<div style="border: 1px solid #ccc; padding: 2px;"> 1 ▲ 2 3 4 5 6 ▼ </div>	<div style="border: 1px solid #ccc; padding: 2px;"> january ▲ february march april may june ▼ </div>	<div style="border: 1px solid #ccc; padding: 2px;"> sunday ▲ monday tuesday wednesday thursday friday ▼ </div>

ctrl+click for multiple selection

from: 27 / 02 / 2012 13:00

Related to the time zone: Europe/Rome

Recurrence status Active

Owner Giorgio Cantoni

Available options for scheduling are shown: daily, weekly, first or last day of month; or a specific date and time. Some of the options can be combined to ensure maximum flexibility.

Periodic execution can be suspended and reactivated simply by changing the value of the "Scheduling status" listbox.

It is also possible to modify the "owner": the user receiving summary reports for executions of this configuration, and who will be able to monitor execution in real time (with UI notifications).

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

The second section shows a log of past module executions (“Available modules” tab) or modules scheduled to run in the future, or executing at the time this page is invoked (“List of items planned or executing”).

Available modules [List of items planned or executing](#)

DataExchange Modules Logs

Filter by configuration: with errors:

Pid	ID	Application	Configuration	Insert	Update	Delete	Init	Time	
9561	0	db.utils.dbfitness		0	0	0	20-01-2011 08:00	00:00:01	
9560	475	importer	E-mail Marketing Consumer Report 2008 - IT - Italia	855	0	0	20-01-2011 08:00	00:00:03	
9559	0	db.utils.dbfitness		0	0	0	20-01-2011 06:15	00:00:01	
9558	1035	importer	contactlab.com - Paper Netcomm	589	0	0	20-01-2011 06:15	00:00:01	
9557	0	db.utils.dbfitness		0	0	0	20-01-2011 06:01	00:00:02	
9556	823	importer	contactlab.com - paper	7,015	0	0	20-01-2011 06:00	00:00:05	

Filter by configuration allows showing past requests according to the final result (success or error). When an error or warning occurred, a warning sign icon appears and if the diagnostic log file is available it can be downloaded by clicking on the attachment icon.

Available modules [List of items planned or executing](#)

DataExchange Modules Logs

Filter by configuration: with errors:

Pid	ID	Application	Configuration	Insert	Update	Delete	Init	Time	
9104	1035	importer	contactlab.com - Paper Netcomm	0	0	0	23-12-2010 06:15	00:00:00	
9044	1035	importer	contactlab.com - Paper Netcomm	0	0	0	19-12-2010 06:15	00:00:00	
9036	1035	importer	contactlab.com - Paper Netcomm	0	0	0	18-12-2010 06:15	00:00:00	

In the “List of items planned or executing” tab, scheduled or currently running configurations are shown.

Available modules [List of items planned or executing](#)

Requested or running modules

#	Module	Configuration	Requested on the	To be executed on	Status
10137183	data-exchange.importer	343	30/09/2009 09:44	30/09/2009 09:44	running
10046888	data-exchange.importer	679,im:0	21/09/2009 08:00	21/09/2009 08:00	running
10046897	data-exchange.importer	475,im:0	21/09/2009 08:00	21/09/2009 08:00	running
10046758	data-exchange.importer	749,im:0	21/09/2009 06:30	21/09/2009 06:30	running
10046723	data-exchange.importer	750,im:0	21/09/2009 06:10	21/09/2009 06:10	running
10042346	data-exchange.importer	665,im:0	20/09/2009 22:00	20/09/2009 22:00	running
10042352	data-exchange.importer	669,im:0	20/09/2009 22:00	20/09/2009 22:00	running
10041103	data-exchange.report	684,im:0	20/09/2009 09:00	20/09/2009 09:00	running
10041071	data-exchange.importer	679,im:0	20/09/2009 08:00	20/09/2009 08:00	running
10041078	data-exchange.importer	475,im:0	20/09/2009 08:00	20/09/2009 08:00	running
10040898	data-exchange.importer	749,im:0	20/09/2009 06:30	20/09/2009 06:30	running
10040876	data-exchange.importer	750,im:0	20/09/2009 06:10	20/09/2009 06:10	running
10036086	data-exchange.importer	665,im:0	19/09/2009 22:00	19/09/2009 22:00	running
10036089	data-exchange.importer	669,im:0	19/09/2009 22:00	19/09/2009 22:00	running
10034411	data-exchange.importer	679,im:0	19/09/2009 08:00	19/09/2009 08:00	running
10034420	data-exchange.importer	475,im:0	19/09/2009 08:00	19/09/2009 08:00	running
10034361	data-exchange.importer	749,im:0	19/09/2009 06:30	19/09/2009 06:30	running

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

9. Standard ETL function library

This is a list of ETL functions already available (as an optional configuration) in ContactLab. Standard ETL functions are applied at the row level; i.e. they are configured on specific fields and will execute in the context of a specific row being processed.

Customized ETL functions outside of this list can implement almost arbitrarily complex requirements, but will require a specific quotation from your Account/Sales for custom development work.

9.1 Basic::stringDateFormat

Transforms custom date formats to the standard yyyy-mm-dd format.

9.2 Basic::getDomainFromEmailAddress

Extracts the domain part of an email address from a complete email address

9.3 Basic::getIntFromBoolean

Normalizes true and false values into integers (true: 1, false: 0)

9.4 Basic::trimChars

Returns a copy of the input string, with leading and trailing whitespace removed

9.5 Basic::force

Unconditionally sets a field/value irrespective of what is specified in the DataExchange input source.

9.6 Basic::integerToBinaryString

Transforms an integer value into a string containing its binary representation (e.g. "6" becomes "110").

9.7 Basic::semicolonSeparated2bitmask

Creates a bitstring representation out of a sequence of integer values. Requires a constant and configured bitstring length.

E.g. suppose we have a 20-positions bitstring representing categories of independent interests for a user profile. The current user profile specifies "1;7;13" as the list of applicable interest categories (1, 7 and 13 are indexes in a fixed list and can mean anything, such as "automotive", "sports", and "financial"). This function will generate the string 00000001000001000001 where positions 1, 7 and 13 (right to left) are set to value 1.

Frequently used with ContactLab's Planner module to enable targeting on arbitrary profile attributes.

9.8 FieldValueMaintainer::dontChangeIfFieldValueIs

Enable specifying a "N/A" value in the input source used to mean "do not change value for this field". The N/A value is a configured parameter.

E.g. suppose the configured N/A value is "VOID". If the value "VOID" is found in a column in the input source, the already existing column value will not be touched.

9.9 FieldValueMaintainer::genericTranscode

Transcode specific values in input fields into 1:1 configured values in database.

E.g. for a "gender" column "F" might be transcoded to 0 and "M" to 1.

9.10 LookupTable::checkField

Looks for a value in a lookup table. If found, returns a field in the lookup table for the matching row, or a fixed value. If not found, a fixed value is returned.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

9.11 Zone::miscellanea

This is specific to the Italian market. Various "Zone" ETL functions are available to transcode to and from Italian Cities, Provinces and Regions names and ID into each other with geographical bonding rules (e.g. from a City to its containing Region name or ID). IDs are indexes in standard, always available and updated lookup tables in ContactLab; IDs are used to enhance performance of complex planning filters in lieu of descriptive names. Zip codes to Province/Region and Province/Region to Nielsen Area ID transcoding functions are also already available in this subset.

10. DataExchange Post-Actions

A *post-action* is an automatic operation which can be configured to run after a successful DataExchange execution.

The following *post-actions* are available and can be configured on request. Custom configuration requires additional work so please contact your Account or Sales manager in order to receive a quote for the effort.

Additional post-actions can be created on demand with a custom development quotation.

10.1 Chained DataExchange Modules

It is possible to have multiple DataExchange operations configured to start automatically in a chain or sequence. The chain will interrupt at the first "broken link" (a DataExchange module completing unsuccessfully).

10.2 Start a Delivery after a DataExchange Operation

A delivery can automatically be started after a successful DataExchange operation.

10.3 DB Fitness

You can automatically remove recipients that either unsubscribed or were inserted in your blacklist/suppression list.

10.4 Duplicate Remover

After updating your database, you can have this automatic process identify multiple copies of the same email address and remove all but one of them. The one with the highest primary key (usually the most recent) will remain; all other duplicated rows will be removed.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

11. Diagnostics messages

Error code	Error message	Possible causes	Possible solutions
DAEX100	Record insertion failed {0}	It usually occurs in the DataImporter and DataUpdater in case of failure of an insertion for sql reasons (value not valid, syntax error..)	Verify if the fields structure of the database in the platform correspond to the one in the file/db source and that the field control (eg. primary key) is correct.
DAEX101	Record updating failed {0}	It usually occurs in the DataUpdater in case of failure of an updating for sql reason (value not valid, syntax error..) or because the updating request didn't find the requested record.	Verify that the fields structure of the database in the platform correspond to the one in the file/db source and that the field control (eg. primary key) is correct. Verify that the user is present in the db of the platform: if not contact our Customer Care.
DAEX102	Record elimination failed {0}	It usually occurs in the DataUpdater in case of a cancellation failure for sql reasons (value not valid, syntax error..) or because the updating request didn't find the requested record.	Verify that the fields structure of the database in the platform correspond to the one in the file/db source and that the field control (eg. primary key) is correct. Verify that the user is present in the db of the platform: if not contact our Customer Care.
DAEX104	Control code not found using the index {0}	It usually occurs in the DataUpdater when the code that decide if carry out with the insert, update or delete is not found in the dedicated column that should host this specific value (operation field).	Verify that the operation field is present and that it contain the correct values. The values have been defined in the activation form that is filled in by the customer during the setup stage and that is been given back to his/her Account.
DAEX105	Number of indexes allowed into the line out of range: {0}	It usually occurs in the DataUpdater or DataImporter with ETL active system when the number of columns that are in the file are different from the ones told in the configuration.	Contact Customer Care

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Error code	Error message	Possible causes	Possible solutions
DAEX150	SQL error, message received: {0}	It usually occurs in all DataExchange when SQL exceptions are provoked and that are not referable to a particular problem.	Contact Customer Care
DAEX200	User db n. {0} seems to be busy by campaign {1} in status {2}	It usually occurs in all DataExchange when their execution is done on their user db that is currently in use in that specific moment (while a campaign is running out..). The message also shows the Id of the campaign that keeps the user db busy and the status of the sending.	If there is a campaign outgoing, wait until the end. If the deployment is blocked in the "Communicate" area or if there is no campaign outgoing, contact Customer Care.
DAEX201	The ContactLab user db is not available at the moment, message received {0}	It usually occurs for all components of the DataExchange when the user db in the platform is not available (for example for temporary connection problems)	Contact Customer Care
DAEX301	Source non available, message received: {0}	It usually occurs when the DataImporter or the DataUpdater doesn't find the source file (csv/xml) or it is not able to read it for authorization reasons.	Verify that the file is in the path and that it has the name that has been specified in the activation form filled in by the customer during the set up stage and that has been given back to his own Account.
DAEX302	The database source is not available, message received: {0}	It usually occurs when the DataExchange tries to enter into an external db source in order to do the import but it doesn't find it or is not able to read it for authorization reasons on the used account.	Verify that the data of the db (host, chart, etc..) correspond to the ones inserted into the activation form during the set up stage and given back to his own Accountant. Verify that the user has all the necessary authorizations.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Error code	Error message	Possible causes	Possible solutions
DAEX304	The remote authentication failed, message received: {0}	This message occurs when a DataExchange tries to enter into an external source, file or db, but the login details (username and password) are incorrect.	Verify that the file is in the path and that it has the name that has been specified in the activation form filled in by the customer during the set up stage and that has been given back to his own Accountant and that the login details to the ftp space (if managed by the customer) are correct.
DAEX305	Connection attempt failed, message received: {0}	It occurs when a DataExchange tries to enter into an external source, file or db, but the communication with the source server expires. It can depend on the missing authorization via firewall from the customer side to the IP from which ContactLab is connected to or because the source service is not active (ftp server, sftp, ftps, db down).	If the ftp space is managed by the customer, verify with your own technical department that everything is working properly. If everything is correct but the problem is still there, contact our Customer Care
DAEX306	There was a problem when attempting to delete/remove source files, error message: {0}	An error occurred when DataCollector tried to delete or rename the external file source.	Typically caused by permission problems on the folders where affected files are located.
DAEX307	There was a problem when attempting to delete/remove the semaphore file, error message: {0}	An error occurred when Poller tried to delete or rename the semaphore files.	Typically caused by permission problems on the folders where affected files are located.
DAEX900	Error not classified {0}	It usually occurs in case of not classified errors that are not present in the ones listed.	Contact Customer Care

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

Error code	Error message	Possible causes	Possible solutions
DAEX901	Problem during the sending of the report, message received: {0}	This message occurs in case of problems in communicating the report via email. The addresses shown as addressees of the report could not be spelled correctly.	Contact Customer Care
DAEX999	Process interrupted {0}	It can depend on the excessive last of the DataExchange process due to unknown reasons so it remains "dangling".	Contact Customer Care

12. Frequently Asked Questions & Answers

You have too many options available. What is your suggested configuration?

Our suggested configuration for any DataExchange is:

- Primary key (USER_PK) managed by you
- DataUpdater with CSV or XML files.

This configuration, although a little more difficult to set up, will guarantee the most flexibility and will grow with your databases. Millions of updates a day are not an issue if performed as updates with a DataUpdater; while refreshing a database of millions of recipients (such as with a DataImporter) will sooner or later become too slow.

By keeping control of your primary key you can track events for your recipients across the history of their relationship with you. Email addresses change – that's a fact of life. If you do not recognize this, you will sooner or later run into problems.

Remote database updates are fashionable and appear so simple to set up but they transfer to your IT department some of the availability and capacity issues you are trying to avoid by outsourcing outbound email management to ContactLab, so it usually isn't a very good idea. Also, having a database open to an external system across the Internet is always a security risk. We cannot guarantee your security perimeter – although we obviously do guarantee ours! And that's why we will never allow you direct access to our database servers.

If you really cannot setup an automated file transfer, there's the option of hosting a copy of your database in our farm, since we also have a housing/hosting business offering.

Can I use encryption to protect data transferred to ContactLab?

ContactLab natively supports public/private key encryption with PGP or GPG. Contact Customer Care to exchange public keys.

Can I use compressed DataImporter/DataUpdater input source files?

Yes, the ZIP (.zip), GZIP (.gz) and BZIP2 (.bz2) format are automatically recognized, according to the filename "extension" (the characters placed after the rightmost dot character in the filename).

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

How can a primary key be managed in ContactLab?

ContactLab natively supports an external (customer-managed) primary key in any user database, provided it is a positive integer. We only support positive integer for performance reasons; it is not possible to use a differently typed key. And we do not support email addresses as primary keys for a number of reasons (the most important one being: people change email addresses more frequently than one could think – and we're quite in a good position to know this for sure).

If you have a positive integer primary key or if you can build a synthetic key from your own, by systematically including it in DataExchange datasource, you will ensure ContactLab view of your recipients will be consistently aligned with your own. For instance, events for a given recipient in multiple deliveries will be currently tracked to the same recipient. Primary key consistency, moreover, enables a quite efficient use for DataUpdater allowing small and frequent synchronizations even with huge recipient databases.

A primary key must by definition be unique in a given user database: it is not necessarily unique across *all* user databases.

If you do not have a suitable primary key in your origin datasource, you can have ContactLab managed it automatically; ContactLab will create a new primary key for every new record you add to your user database (once again, primary key is unique in a given user database). However, since ContactLab has no knowledge of what your primary key is, if you add multiple copies of the same recipient, they will be identified by different primary keys. ContactLab will be unable to help you track events across deliveries (across updates to the database).

Customizations of the DataExchange modules can be implemented to delegate to ContactLab maintenance of the relationship between your primary key (when it does not fit an integer, possibly even when composed by more than one field). If you are interested in an evaluation of this approach contact your Account.

Why is my User Database locked after a failed DataExchange operation?

In ContactLab we follow a simple principle: contrary to web pages, once an email has been sent, it cannot be corrected nor recalled. We believe sending a wrong email or sending an email to a recipient who doesn't want it is a much more serious incident than failing to send an email. So when a DataExchange operation fails, our assumption is your User Database failed some important updates and we leave it "locked" – no delivery can be sent when the database is locked. A delivery will retry itself for some time, so if you repeat the DataExchange operation and this time it completes successfully, it will proceed. After some time it will enter a failed state.

You can ask your DataExchange configuration to ignore some error. This requires manual configuration only because we want to discuss with you to make sure you are well aware of the dangers.

Can I have more than one DataExchange configuration active on the same User Database?

Yes, you can. Schedule them carefully to avoid overlaps and remember the User Database remains locked during each execution. Execution will be serialized, in order to preserve consistency of data. You can also "chain" DataExchange configurations so that they executed in a given sequence without risking interlocking issues.

Can I automatically add a new row when a DataUpdater 'U' operations fails because the row is not there?

Yes, you can have your DataUpdater configured so it will automatically transform an U (update) instruction to I (insert) if the master condition for that row is not matched.

ContactLab DataExchange	Version <201705.1>
Configuration Guide	Date: 2017-05-03
	<i>Proprietary and confidential</i>

How long are detailed data on events available?

Detailed data (including personal information such as email address of the recipient and all events) are available for 12 months. After this period, they are aggregated so that summary info and indicators on campaigns are available until customer can access ContactLab, but details are deleted permanently. This ensures compliance with the current regulations and best practices on personal data protection for marketing use. Using a DataExporter feed, you can receive all event details and archive them with a different retention policy, if you have the need. It is possible to ask for a shorter retention period, however we will not accept a retention period shorter than 90 days to ensure some of the mandatory unsubscribe mechanisms work for at least this length of time. Please contact our CustomerCare or our dedicated Account if you are interested in shortening the retention period.

When is feedback data available via the Exporter?

Exporter data is aggregated twice a day, every day, with automated processes scheduled to start at 11.00 CET and 23.00 CET. The aggregation process is, in normal circumstances, completed at most 1h after the indicated start time.

13. Contacts

The ContactLab Helpdesk / Customer Care is always ready to examine your questions. Just open a new ticket from our web UI (Support section), on our support website <https://support.contactlab.com>, or send an email to helpdesk@contactlab.com. Customer with Premium support levels can also call the special Premium Support phone number.